


# Demorad Setup Guide


## ► Installing drivers for Demorad

- Power up the Demorad and connect to it via Mini USB port.
- Unzip the ADI\_Demo\_Driver.zip in the Software folder.
- Find the “BF707 Bulk Device” in your Control Panel Devices and Printers window.
- Open the Properties of the device.
  - Edit the properties to manually install the drivers from the unzipped folder of drivers.
  - More detail on page 2.
- Run the DemoRadTool-x32.exe file.



# Demorad Setup Guide


## More detailed Driver Installation\*



1


Find the device in the Printers and Devices window.

“BF707 Bulk Device”




2

Select properties in the Hardware Tab.




3

Change Settings in the Device Properties. This requires administration rights.



4

Install Drivers for the device



5

Browse my computer for driver software



6

Select the unzipped ADI\_Demo\_Driver folder and click next.

\*This guide is done on Windows 7. There may be differences on other OS.